



Kodi voor beginners

2 Euro

Stap 1: U klikt met de linkermuisknop op 'Microsoft Store - 1 actief venster (knop)'




Stap 2: U klikt met de linkermuisknop op 'Zoekknop (knop op app-balk)'




Stap 3: U voert gegevens in op het toetsenbord op 'Microsoft Store (venster)'


KODI




Stap 4: U klikt met de linkermuisknop op 'Kodi App (lijstonderdeel)'




Stap 5: U klikt met de linkermuisknop op 'Kodi kopen - Microsoft Store nl-NL'





Stap 6: Instaleer Kodi



Stap 7: Start Kodi



Stap 8: Zet de taal op Nederlands en we kiezen de Confluence skin om de setup te doen, hiermee zijn de voorbeelden gemaakt.



Hierna gaan we Kodi afconfigureren.

**Interface Tab Regionaal : de Taal
Diensten ->Algemeen Hostnaam
→Beheer toestaan van de afstandsbediening
→ UPnP Alles toestaan om te delen
→ Airplay voor Apple
→ Weer voor het weer.**

Speler

Taal voor ondertitels

Addons

De extra zaken die kodi leuk maken.

Voeg Items toe.

Links op Meer verkrijgen.

Zoeken naar Addons en toevoegen.

Lees de facebook kodi groepen en zoek met Google naar repository

Bekende repositories	..Kodil , Steptoos, en vele andere kan je vinden.
Illegaal	Iedereen die zaken aanbied wat als illegaal aangemerkt kan worden zal op last van S.B. van internet worden verwijderd.
Installeer als zip bestand	b.v. Retrospect moet je vanaf de site downloaden en apart updaten in Kodi deze gaat niet automatisch
Andere platformen	Voor elk os is er een Kodi zelfs voor de raspberry pi.

1 Default keyboard controls

The default [keymap](#) can be found at

<https://github.com/xbmc/xbmc/blob/master/system/keymaps/keyboard.xml>

Key	Global	Video playback	Music visualisation
0 (zero)		Go between the two last channels (<i>live TV channel</i>) OR Go to "now" on EPG/TV guide.	
A		Audio delay control	
B	Live TV: Schedule recording timers	Live TV: Schedule recording timers	
C	Contextual menu	Playlist	
D	Move item down (<i>Playlist editor & Favorites window</i>)		
E	Live TV EPG/TV guide	Live TV EPG/TV guide	
F	Fast forward	Fast forward	Fast forward
H	Live TV channels window	Live TV channels window	
I	Info	Info	Info
J	Live TV: Radio channels window	Live TV: Radio channels window	
K	Live TV recordings window	Live TV recordings window	
L		Next subtitle	Lock preset

Key	Global	Video playback	Music visualisation
M	<ul style="list-style-type: none"> "Menu" (sidebar menu on the default skin) Move (<i>File manager</i>) 	Player controls (OSD)	Player controls (OSD)
N			Current playlist window
O		Codec info	Codec info
Ctrl+↑ Shift+O		Codec Info 2 (Additional info. E.g. bitrates, cache and skips/drops)	Codec Info 2 (additional info. E.g. bitrates, cache and skips/drops)
Ctrl+↑ Shift+D	Toggle debug logging	Toggle debug logging	Toggle debug logging
P	Play	Play	Visualisation preset list
alt+← or →		Decrease/Increase Playback Speed - (0.8x - 1.5x speed)	
		Only works when <i>Sync Playback to Display</i> is enabled which will Disable Audio Passthrough	
Q	Queue		
	<ul style="list-style-type: none"> Rewind Rename (<i>File manager</i>) 		
R		Rewind	Rewind
S	Shutdown menu	Shutdown menu	Show preset
Ctrl+S	Screenshot	Screenshot	Screenshot
T		Toggle subtitles on and off	
Ctrl+T		Subtitle position control	
U	Move item up (<i>Playlist editor & Favorites window</i>)		
V		Teletext	Visualisation settings
W	Marked as watched / unwatched		

Key	Global	Video playback	Music visualisation
X	Stop	Stop	Stop
Y	Switch/choose player. For example, can be used to switch between internal player or a UPnP target player.	Switch/choose player	Switch/choose player
Z		Zoom/aspect ratio	
Space	<ul style="list-style-type: none"> Pause/Play Current playlist window (<i>video & music listings</i>) Highlight (<i>File manager</i>) 	Pause/Play	Pause/Play
←	Left	<ul style="list-style-type: none"> Seek step backward. 1x 10s, 2x 30s, 3x 1m, 4x 3m... Prev channel group (<i>live TV</i>) 	Seek step backward. 1x 10s, 2x 30s, 3x 1m, 4x 3m...
→	Right	<ul style="list-style-type: none"> Seek step forward. 1x 10s, 2x 30s, 3x 1m, 4x 3m... Next channel group (<i>live TV</i>) 	Seek step forward. 1x 10s, 2x 30s, 3x 1m, 4x 3m...
↑	Up	<ul style="list-style-type: none"> Seek step forward 10min OR Next chapter (<i>videos</i>) Channel up (<i>live TV</i>) 	Next track
↓	Down	<ul style="list-style-type: none"> Step back 10min OR Prev chapter (<i>videos</i>) Channel down (<i>live TV</i>) 	Previous track
Ctrl + ←		Variable seek backwards	Variable seek backwards
Ctrl + →		Variable seek forward	Variable seek forward

Key	Global	Video playback	Music visualisation
Ctrl +↑		Move subtitles up	
Ctrl +↓		Move subtitles down	
PageUp	Page up	Skip to next queued video or next chapter if no videos are queued.	Increase rating
PageDown	Page down	Skip to previous queued video or previous chapter if no videos are queued.	Decrease rating
↵ Enter return	Select	Player controls (OSD)	Player controls (OSD)
← Backspace	Back	Back	Back
Esc	Previous menu OR Home screen	Exit full screen	
. period	Skip forward	Seek step forward. 1x 10s, 2x 30s, 3x 1m, 4x 3m...	Seek step forward. 1x 10s, 2x 30s, 3x 1m, 4x 3m...
, comma	Skip backward	Seek step backward. 1x 10s, 2x 30s, 3x 1m, 4x 3m...	Seek step backward. 1x 10s, 2x 30s, 3x 1m, 4x 3m...
' quote		Small seek step backwards 7 seconds	
Tab ⇌	Fullscreen playback	Fullscreen playback	Fullscreen playback
PrintSrc	Screenshot	Screenshot	Screenshot
F8	Mute	Mute	Mute
- minus	Volume down	Volume down	Volume down
+ plus	Volume up	Volume up	Volume up
= equals	Volume up	Volume up	Volume up
\ backslash	Toggle between fullscreen/windowed mode	Toggle between fullscreen/windowed mode	Toggle between fullscreen/windowed mode
[left bracket		Seek step forward 10min	
] right bracket		Seek step backward 10min	

Key	Global	Video playback	Music visualisation
CTRL+END	Exit Kodi (<i>Only on Home Screen</i>)		
DEL	Delete file (<i>if enabled in settings</i>)	Remove from playlist (<i>Playlist editor only</i>)	Remove from playlist (<i>Playlist editor only</i>)
Home	Jump to the top of the menu (..)		
[numbers] then Return		Jump to that time in playback. (E.g., 1+2+3+4+return will jump to 12 minutes and 34 seconds.)	Jump to that time in playback. (E.g., 1+2+3+4+return will jump to 12 minutes and 34 seconds.)
[numbers] then ←		Jump backwards in that amount of time. (E.g., 1+0+← will jump back 10 seconds.)	Jump backwards in that amount of time. (E.g., 1+0+← will jump back 10 seconds.)
[numbers] then →		Jump forward in that amount of time. (E.g., 1+0+→ will jump forward 10 seconds.)	Jump forward in that amount of time. (E.g., 1+0+→ will jump forward 10 seconds.)
↑ Shift+LETTER	Jump to that letter in a list		

2 Mouse controls

Key	Description
Left Click on item	Select
Middle Click on item	Queue to playlist
Right Click on item	Context menu
Right Click on blank area	Back
Mouse Wheel Up	Up
Mouse Wheel Down	Down

3 Picture slide show controls

Key	Description
0	Zoom Normal (100%)

1 Zoom Level 1

2 Zoom Level 2

3 Zoom Level 3

4 Zoom Level 4

5 Zoom Level 5

6 Zoom Level 6

7 Zoom Level 7

8 Zoom Level 8

9 Zoom Level 9

R Rotate

T Info (EXif data)

. **period** Next picture

, **comma** Previous picture

+ **plus** Zoom in

- **minus** Zoom out

4 Platform specific controls

4.1 Windows, Live, and Linux

☰ Menu (Menu key): Contextual menu

4.2 Mac

⌘ Cmd+**Q** to quit

⌘ Cmd+**H** and **⌘ Cmd**+**M** to hide/minimize to the dock

⌘ Cmd+**F** to toggle fullscreen

⌘ Cmd+**S** to take a screen shot

5 Customizing buttons through the GUI

Main page: **Add-on:Keymap Editor**

Users can customize [keymaps](#) for remotes in GUI by using the community [Keymap Editor](#) add-on.

<https://kodi.wiki> voor meer informatie.

<https://kodi.tv/> De website,